


## Lab 5.5.2: Challenge Spanning Tree Protocol

## Topology Diagram



## Addressing Table

Device (Hostname)	Interface	IP Address	Subnet Mask	Default Gateway
S1	VLAN 99	172.17.99.11	255.255.255.0	N/A
S2	VLAN 99	172.17.99.12	255.255.255.0	N/A
S3	VLAN 99	172.17.99.13	255.255.255.0	N/A
PC1	NIC	172.17.10.21	255.255.255.0	172.17.10.12
PC2	NIC	172.17.20.22	255.255.255.0	172.17.20.12
PC3	NIC	172.17.30.23	255.255.255.0	172.17.30.12

## Port Assignments – Switch 2

Ports	Assignment	Network
Fa0/1 – 0/4	802.1q Trunks (Native VLAN 99)	172.17.99.0 /24
Fa0/5 – 0/10	VLAN 30 – Guest (Default)	172.17.30.0 /24
Fa0/11 – 0/17	VLAN 10 – Faculty/Staff	172.17.10.0 /24
Fa0/18 – 0/24	VLAN 20 – Students	172.17.20.0 /24

## Learning Objectives

Upon completion of this lab, you will be able to:

- Cable a network according to the topology diagram
- Erase the startup configuration and reload the default configuration, setting a switch to the default state
- Perform basic configuration tasks on a switch
- Configure VLAN Trunking Protocol (VTP) on all switches
- Observe and explain the default behavior of Spanning Tree Protocol (STP, 802.1D)
- Modify the placement of the spanning tree root
- Observe the response to a change in the spanning tree topology
- Explain the limitations of 802.1D STP in supporting continuity of service
- Configure Rapid STP (802.1W)
- Observe and explain the improvements offered by Rapid STP

## Task 1: Prepare the Network

### Step 1: Cable a network that is similar to the one in the topology diagram.

You can use any current switch in your lab as long as it has the required interfaces shown in the topology diagram. The output shown in this lab is based on Cisco 2960 switches. Other switch models may produce different output.

Set up console connections to all three switches.

### Step 2: Clear any existing configurations on the switches.

Clear NVRAM, delete the vlan.dat file, and reload the switches. Refer to Lab 2.5.1 for the procedure. After the reload is complete, use the **show vlan** privileged EXEC command to confirm that only default VLANs exist and that all ports are assigned to VLAN 1.

Switch#**show vlan**

VLAN	Name	Status	Ports
1	default	active	Fa0/1, Fa0/2, Fa0/3, Fa0/4 Fa0/5, Fa0/6, Fa0/7, Fa0/8 Fa0/9, Fa0/10, Fa0/11, Fa0/12 Fa0/13, Fa0/14, Fa0/15, Fa0/16 Fa0/17, Fa0/18, Fa0/19, Fa0/20 Fa0/21, Fa0/22, Fa0/23, Fa0/24

```

Gig1/1, Gig1/2
1002 fddi-default          active
1003 token-ring-default    active
1004 fddinet-default       active
1005 trnet-default         active

```

### Step 3: Disable all ports by using the shutdown command.

Ensure that the initial switch port states are inactive with the **shutdown** command. Use the **interface-range** command to simplify this task. Repeat these commands on each switch.

```

Switch(config)#interface range fa0/1-24
Switch(config-if-range)#shutdown
Switch(config-if-range)#interface range gi0/1-2
Switch(config-if-range)#shutdown

```

## Task 2: Perform Basic Switch Configurations

Configure the S1, S2, and S3 switches according to the following guidelines:

- Configure the switch hostname.
- Disable DNS lookup.
- Configure an EXEC mode password of **class**.
- Configure a password of **cisco** for console connections.
- Configure a password of **cisco** for vty connections.

(Output for S1 shown)

```

Switch>enable
Switch#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#hostname S1
S1(config)#enable secret class
S1(config)#no ip domain-lookup
S1(config)#line console 0
S1(config-line)#password cisco
S1(config-line)#login
S1(config-line)#line vty 0 15
S1(config-line)#password cisco
S1(config-line)#login
S1(config-line)#end
%SYS-5-CONFIG_I: Configured from console by console
S1#copy running-config startup-config
Destination filename [startup-config]?
Building configuration...
[OK]

```

## Task 3: Configure Host PCs

Configure the Ethernet interfaces of PC1, PC2, and PC3 with the IP address, subnet mask, and gateway indicated in the addressing table at the beginning of the lab.

## Task 4: Configure VLANs

### Step 1: Configure VTP.

Configure VTP on the three switches using the following table. Remember that VTP domain names and passwords are case-sensitive. The default operating mode is server.

Switch Name	VTP Operating Mode	VTP Domain	VTP Password
<b>S1</b>	<b>Server</b>	<b>Lab5</b>	<b>cisco</b>
<b>S2</b>	<b>Client</b>	<b>Lab5</b>	<b>cisco</b>
<b>S3</b>	<b>Client</b>	<b>Lab5</b>	<b>cisco</b>

```
S1(config)#vtp mode server
Device mode already VTP SERVER.
S1(config)#vtp domain Lab5
Changing VTP domain name from NULL to Lab5
S1(config)#vtp password cisco
Setting device VLAN database password to cisco
S1(config)#end
```

```
S2(config)#vtp mode client
Setting device to VTP CLIENT mode
S2(config)#vtp domain Lab5
Changing VTP domain name from NULL to Lab5
S2(config)#vtp password cisco
Setting device VLAN database password to cisco
S2(config)#end
```

```
S3(config)#vtp mode client
Setting device to VTP CLIENT mode
S3(config)#vtp domain Lab5
Changing VTP domain name from NULL to Lab5
S3(config)#vtp password cisco
Setting device VLAN database password to cisco
S3(config)#end
```

## Step 2: Configure Trunk Links and Native VLAN

Configure trunking ports and native VLAN. For each switch, configure ports Fa0/1 through Fa0/4 as trunking ports. Designate VLAN 99 as the native VLAN for these trunks. Use the **interface range** command in global configuration mode to simplify this task. Remember that these ports were disabled in a previous step and must be re-enabled using the **no shutdown** command.

```
S1(config)#interface range fa0/1-4
S1(config-if-range)#switchport mode trunk
S1(config-if-range)#switchport trunk native vlan 99
S1(config-if-range)#no shutdown
S1(config-if-range)#end
```

```
S2(config)# interface range fa0/1-4
S2(config-if-range)#switchport mode trunk
S2(config-if-range)#switchport trunk native vlan 99
S2(config-if-range)#no shutdown
S2(config-if-range)#end
```

```
S3(config)# interface range fa0/1-4
S3(config-if-range)#switchport mode trunk
```

```
S3(config-if-range)#switchport trunk native vlan 99
S3(config-if-range)#no shutdown
S3(config-if-range)#end
```

### Step 3: Configure the VTP server with VLANs.

VTP allows you to configure VLANs on the VTP server and have those VLANs populated to the VTP clients in the domain. This ensures consistency in the VLAN configuration across the network.

Configure the following VLANs on the VTP server:

VLAN	VLAN Name
VLAN 99	management
VLAN 10	faculty-staff
VLAN 20	students
VLAN 30	guest

```
S1(config)#vlan 99
S1(config-vlan)#name management
S1(config-vlan)#exit
S1(config)#vlan 10
S1(config-vlan)#name faculty-staff
S1(config-vlan)#exit
S1(config)#vlan 20
S1(config-vlan)#name students
S1(config-vlan)#exit
S1(config)#vlan 30
S1(config-vlan)#name guest
S1(config-vlan)#exit
```

### Step 4: Verify the VLANs.

Use the **show vlan brief** command on S2 and S3 to verify that all four VLANs have been distributed to the client switches.

S2#show vlan brief

VLAN	Name	Status	Ports
1	default	active	Fa0/1, Fa0/2, Fa0/4, Fa0/5 Fa0/6, Fa0/7, Fa0/8, Fa0/9 Fa0/10, Fa0/11, Fa0/12, Fa0/13 Fa0/14, Fa0/15, Fa0/16, Fa0/17 Fa0/18, Fa0/19, Fa0/20, Fa0/21 Fa0/22, Fa0/23, Fa0/24, Gi0/1 Gi0/2
10	faculty-staff	active	
20	students	active	
30	guest	active	
99	management	active	

S3#show vlan brief

VLAN	Name	Status	Ports
1	default	active	Fa0/1, Fa0/2, Fa0/4, Fa0/5 Fa0/6, Fa0/7, Fa0/8, Fa0/9 Fa0/10, Fa0/11, Fa0/12, Fa0/13 Fa0/14, Fa0/15, Fa0/16, Fa0/17 Fa0/18, Fa0/19, Fa0/20, Fa0/21 Fa0/22, Fa0/23, Fa0/24, Gi0/1 Gi0/2
10	faculty-staff	active	
20	students	active	
30	guest	active	
99	management	active	

### Step 5: Configure the management interface address on all three switches.

```
S1(config)#interface vlan99
S1(config-if)#ip address 172.17.99.11 255.255.255.0
S1(config-if)#no shutdown

S2(config)#interface vlan99
S2(config-if)#ip address 172.17.99.12 255.255.255.0
S2(config-if)#no shutdown

S3(config)#interface vlan99
S3(config-if)#ip address 172.17.99.13 255.255.255.0
S3(config-if)#no shutdown
```

Verify that the switches are correctly configured by pinging between them. From S1, ping the management interface on S2 and S3. From S2, ping the management interface on S3.

Were the pings successful? \_\_\_\_\_

If not, troubleshoot the switch configurations and try again.

### Step 6: Assign switch ports to the VLANs.

Assign ports to VLANs on S2. Refer to the port assignments table at the beginning of the lab.

```
S2(config)#interface range fa0/5-10
S2(config-if-range)#switchport mode access
S2(config-if-range)#switchport access vlan 30
S2(config-if-range)#interface range fa0/11-17
S2(config-if-range)#switchport mode access
S2(config-if-range)#switchport access vlan 10
S2(config-if-range)#interface range fa0/18-24
S2(config-if-range)#switchport mode access
S2(config-if-range)#switchport access vlan 20
S2(config-if-range)#end
S2#copy running-config startup-config
Destination filename [startup-config]? [enter]
Building configuration...
[OK]
S2#
```

### Step 7: Re-enable the user ports on S2.

Refer to the topology diagram to determine which switch ports on S2 are activated for end-user device

access. These three ports will be enabled with the **no shutdown** command.

```
S2(config)#interface range fa0/6, fa0/11, fa0/18
S2(config-if-range)#no shutdown
```

## Task 5: Configure Spanning Tree

### Step 1: Examine the default configuration of 802.1D STP.

On each switch, display the spanning tree table with the **show spanning-tree** command. The output is shown for S1 only. Root selection varies depending on the BID of each switch in your lab.

```
S1#show spanning-tree
```

#### VLAN0001

```
Spanning tree enabled protocol ieee
Root ID    Priority    32769
           Address    0019.068d.6980
           This bridge is the root
           Hello Time  2 sec  Max Age 20 sec  Forward Delay 15 sec
```

```
Bridge ID  Priority    32769  (priority 32768 sys-id-ext 1)
           Address    0019.068d.6980
           Hello Time  2 sec  Max Age 20 sec  Forward Delay 15 sec
           Aging Time  300
```

Interface	Role	Sts	Cost	Prio.Nbr	Type
-----	----	---	-----	-----	-----
Fa0/1	Desg	FWD	19	128.3	P2p
Fa0/2	Desg	FWD	19	128.4	P2p
Fa0/3	Desg	FWD	19	128.5	P2p
Fa0/4	Desg	FWD	19	128.6	P2p

#### VLAN0010

```
Spanning tree enabled protocol ieee
Root ID    Priority    32778
           Address    0019.068d.6980
           This bridge is the root
           Hello Time  2 sec  Max Age 20 sec  Forward Delay 15 sec
```

```
Bridge ID  Priority    32778  (priority 32768 sys-id-ext 10)
           Address    0019.068d.6980
           Hello Time  2 sec  Max Age 20 sec  Forward Delay 15 sec
           Aging Time  300
```

Interface	Role	Sts	Cost	Prio.Nbr	Type
-----	----	---	-----	-----	-----
Fa0/1	Desg	FWD	19	128.3	P2p
Fa0/2	Desg	FWD	19	128.4	P2p
Fa0/3	Desg	FWD	19	128.5	P2p
Fa0/4	Desg	FWD	19	128.6	P2p

#### VLAN0020

```
Spanning tree enabled protocol ieee
Root ID    Priority    32788
           Address    0019.068d.6980
```

**This bridge is the root**

Hello Time 2 sec Max Age 20 sec Forward Delay 15 sec

**Bridge ID** Priority 32788 (priority 32768 sys-id-ext 20)

Address 0019.068d.6980

Hello Time 2 sec Max Age 20 sec Forward Delay 15 sec

Aging Time 300

Interface	Role	Sts	Cost	Prio.Nbr	Type
-----	---	---	-----	-----	-----
Fa0/1	Desg	FWD	19	128.3	P2p
Fa0/2	Desg	FWD	19	128.4	P2p
Fa0/3	Desg	FWD	19	128.5	P2p
Fa0/4	Desg	FWD	19	128.6	P2p

**VLAN0030**

Spanning tree enabled protocol ieee

Root ID Priority 32798

Address 0019.068d.6980

**This bridge is the root**

Hello Time 2 sec Max Age 20 sec Forward Delay 15 sec

**Bridge ID** Priority 32798 (priority 32768 sys-id-ext 30)

Address 0019.068d.6980

Hello Time 2 sec Max Age 20 sec Forward Delay 15 sec

Aging Time 300

Interface	Role	Sts	Cost	Prio.Nbr	Type
-----	---	---	-----	-----	-----
Fa0/1	Desg	FWD	19	128.3	P2p
Fa0/2	Desg	FWD	19	128.4	P2p
Fa0/3	Desg	FWD	19	128.5	P2p
Fa0/4	Desg	FWD	19	128.6	P2p

**VLAN0099**

Spanning tree enabled protocol ieee

Root ID Priority 32867

Address 0019.068d.6980

**This bridge is the root**

Hello Time 2 sec Max Age 20 sec Forward Delay 15 sec

**Bridge ID** Priority 32867 (priority 32768 sys-id-ext 99)

Address 0019.068d.6980

Hello Time 2 sec Max Age 20 sec Forward Delay 15 sec

Aging Time 300

Interface	Role	Sts	Cost	Prio.Nbr	Type
-----	---	---	-----	-----	-----
Fa0/1	Desg	FWD	19	128.3	P2p
Fa0/2	Desg	FWD	19	128.4	P2p
Fa0/3	Desg	FWD	19	128.5	P2p
Fa0/4	Desg	FWD	19	128.6	P2p

Note that there are five instances of the spanning tree on each switch. The default STP configuration on Cisco switches is Per-VLAN Spanning Tree (PVST+), which creates a separate spanning tree for each



VLAN (VLAN 1 and any user-configured VLANs).

Examine the VLAN 99 spanning tree for all three switches:

S1#**show spanning-tree vlan 99**

VLAN0099

```
Spanning tree enabled protocol ieee
Root ID      Priority      32867
              Address      0019.068d.6980
              This bridge is the root
Hello Time    2 sec    Max Age 20 sec    Forward Delay 15 sec
```

```
Bridge ID     Priority      32867    (priority 32768 sys-id-ext 99)
              Address      0019.068d.6980
Hello Time    2 sec    Max Age 20 sec    Forward Delay 15 sec
Aging Time    300
```

Interface	Role	Sts	Cost	Prio.Nbr	Type
-----	----	---	-----	-----	-----
Fa0/1	Desg	FWD	19	128.3	P2p
Fa0/2	Desg	FWD	19	128.4	P2p
Fa0/3	Desg	FWD	19	128.5	P2p
Fa0/4	Desg	FWD	19	128.6	P2p

S2#**show spanning-tree vlan 99**

VLAN0099

```
Spanning tree enabled protocol ieee
Root ID      Priority      32867
              Address      0019.068d.6980    This is the MAC address of the root switch (S1 in
this case)
              Cost          19
              Port          3 (FastEthernet0/3)
Hello Time    2 sec    Max Age 20 sec    Forward Delay 15 sec
```

```
Bridge ID     Priority      32867    (priority 32768 sys-id-ext 99)
              Address      001b.0c68.2080
Hello Time    2 sec    Max Age 20 sec    Forward Delay 15 sec
Aging Time    15
```

Interface	Role	Sts	Cost	Prio.Nbr	Type
-----	----	---	-----	-----	-----
Fa0/1	Desg	FWD	19	128.1	P2p
Fa0/2	Desg	FWD	19	128.2	P2p
Fa0/3	Root	FWD	19	128.3	P2p
Fa0/4	Altn	BLK	19	128.4	P2p

S3#**show spanning-tree vlan 99**

VLAN0099

```
Spanning tree enabled protocol ieee
Root ID      Priority      32867
              Address      0019.068d.6980    This is the MAC address of the root switch (S1 in
this case)
              Cost          19
              Port          1 (FastEthernet0/1)
```

Hello Time 2 sec Max Age 20 sec Forward Delay 15 sec

Bridge ID Priority 32867 (priority 32768 sys-id-ext 99)  
Address 001b.5303.1700  
Hello Time 2 sec Max Age 20 sec Forward Delay 15 sec  
Aging Time 300

Interface	Role	Sts	Cost	Prio.Nbr	Type
Fa0/1	Root	FWD	19	128.1	P2p
Fa0/2	Altn	BLK	19	128.2	P2p
Fa0/3	Altn	BLK	19	128.3	P2p
Fa0/4	Altn	BLK	19	128.4	P2p

## Step 2: Examine the output.

Answer the following questions based on the output.

- What is the bridge ID priority for switches S1, S2, and S3 on VLAN 99?
  - S1 \_\_\_\_\_
  - S2 \_\_\_\_\_
  - S3 \_\_\_\_\_
- What is the bridge ID priority for S1 on VLANs 10, 20, 30, and 99?
  - VLAN 10 \_\_\_\_\_
  - VLAN 20 \_\_\_\_\_
  - VLAN 30 \_\_\_\_\_
  - VLAN 99 \_\_\_\_\_
- Which switch is the root for the VLAN 99 spanning tree? \_\_\_\_\_
- On VLAN 99, which spanning tree ports are in the blocking state on the root switch?  
\_\_\_\_\_
- On VLAN 99, which spanning tree ports are in the blocking state on the non-root switches?  
\_\_\_\_\_
- How does STP elect the root switch? \_\_\_\_\_
- Since the bridge priorities are all the same, what else does the switch use to determine the root?  
\_\_\_\_\_

## Task 6: Optimizing STP

Because there is a separate instance of the spanning tree for every active VLAN, a separate root election is conducted for each instance. If the default switch priorities are used in root selection, the same root is elected for every spanning tree, as we have seen. This could lead to an inferior design. Some reasons to control the selection of the root switch include:

- The root switch is responsible for generating BPDUs in STP 802.1D and is the focal point for spanning tree control traffic. The root switch must be capable of handling this additional processing load.
- The placement of the root defines the active switched paths in the network. Random placement is likely to lead to suboptimal paths. Ideally the root is in the distribution layer.

- Consider the topology used in this lab. Of the six trunks configured, only two are carrying traffic. While this prevents loops, it is a waste of resources. Because the root can be defined on the basis of the VLAN, you can have some ports blocking for one VLAN and forwarding for another. This is demonstrated below.

In this example, it has been determined that the root selection using default values has led to under-utilization of the available switch trunks. Therefore, it is necessary to force another switch to become the root switch for VLAN 99 to impose some load-sharing on the trunks.

Selection of the root switch is accomplished by changing the spanning-tree priority for the VLAN. Because the default root switch may vary in your lab environment, we will configure S1 and S3 to be the root switches for specific VLANs. The default priority, as you have observed, is 32768 plus the VLAN ID. The lower number indicates a higher priority for root selection. Set the priority for VLAN 99 on S3 to 4096.

```
S3(config)#spanning-tree vlan 99 ?
forward-time  Set the forward delay for the spanning tree
hello-time    Set the hello interval for the spanning tree
max-age       Set the max age interval for the spanning tree
priority      Set the bridge priority for the spanning tree
root          Configure switch as root
<cr>
```

```
S3(config)#spanning-tree vlan 99 priority ?
<0-61440>  bridge priority in increments of 4096
```

```
S3(config)#spanning-tree vlan 99 priority 4096
S3(config)#exit
```

Set the priority for VLANs 1, 10, 20, and 30 on S1 to 4096. Once again, the lower number indicates a higher priority for root selection.

```
S1(config)#spanning-tree vlan 1 priority 4096
S1(config)#spanning-tree vlan 10 priority 4096
S1(config)#spanning-tree vlan 20 priority 4096
S1(config)#spanning-tree vlan 30 priority 4096
S1(config)#exit
```

Give the switches a little time to recalculate the spanning tree and then check the tree for VLAN 99 on switch S1 and switch S3.

```
S1#show spanning-tree vlan 99
```

```
VLAN0099
Spanning tree enabled protocol ieee
Root ID    Priority    4195
           Address    001b.5303.1700  This is now the MAC address of S3, (the new root
switch)
           Cost        19
           Port        3 (FastEthernet0/1)
           Hello Time   2 sec  Max Age 20 sec  Forward Delay 15 sec

Bridge ID   Priority    32867  (priority 32768 sys-id-ext 99)
           Address    0019.068d.6980
           Hello Time   2 sec  Max Age 20 sec  Forward Delay 15 sec
           Aging Time   300
```

Interface	Role	Sts	Cost	Prio.Nbr	Type
Fa0/1	Root	FWD	19	128.3	P2p
Fa0/2	Altn	BLK	19	128.4	P2p
Fa0/3	Desg	FWD	19	128.5	P2p
Fa0/4	Desg	FWD	19	128.6	P2p

S3#**show spanning-tree vlan 99**

VLAN0099

Spanning tree enabled protocol ieee

Root ID Priority 4195

Address 001b.5303.1700

**This bridge is the root**

Hello Time 2 sec Max Age 20 sec Forward Delay 15 sec

Bridge ID Priority 4195 (priority 4096 sys-id-ext 99)

Address 001b.5303.1700

Hello Time 2 sec Max Age 20 sec Forward Delay 15 sec

Aging Time 300

Interface	Role	Sts	Cost	Prio.Nbr	Type
Fa0/1	Desg	FWD	19	128.1	P2p
Fa0/2	Desg	FWD	19	128.2	P2p
Fa0/3	Desg	FWD	19	128.3	P2p
Fa0/4	Desg	FWD	19	128.4	P2p

Which switch is the root for VLAN 99? \_\_\_\_\_

On VLAN 99, which spanning tree ports are in the blocking state on the new root switch? \_\_\_\_\_

On VLAN 99, which spanning tree ports are in the blocking state on the old root switch? \_\_\_\_\_

Compare the S3 VLAN 99 spanning tree above with the S3 VLAN 10 spanning tree.

S3#**show spanning-tree vlan 10**

VLAN0010

Spanning tree enabled protocol ieee

Root ID Priority 4106

Address 0019.068d.6980

Cost 19

Port 1 (FastEthernet0/1)

Hello Time 2 sec Max Age 20 sec Forward Delay 15 sec

Bridge ID Priority 32778 (priority 32768 sys-id-ext 10)

Address 001b.5303.1700

Hello Time 2 sec Max Age 20 sec Forward Delay 15 sec

Aging Time 300

Interface	Role	Sts	Cost	Prio.Nbr	Type
Fa0/1	Root	FWD	19	128.1	P2p
Fa0/2	Altn	BLK	19	128.2	P2p
Fa0/3	Altn	BLK	19	128.3	P2p
Fa0/4	Altn	BLK	19	128.4	P2p

Note that S3 can now use all four ports for VLAN 99 traffic as long as they are not blocked at the other end of the trunk. However, the original spanning tree topology, with three of four S3 ports in blocking mode, is still in place for the four other active VLANs. By configuring groups of VLANs to use different trunks as their primary forwarding path, we retain the redundancy of failover trunks, without having to leave trunks totally unused.

### Task 7: Observe the response to the topology change in 802.1D STP

To observe continuity across the LAN during a topology change, first reconfigure PC3, which is connected to port S2 Fa0/6, with IP address 172.17.99.23 255.255.255.0. Then reassign S2 port Fa0/6 to VLAN 99. This allows you to continuously ping across the LAN from the host.

```
S2(config)# interface fa0/6
S2(config-if)#switchport access vlan 99
```

Verify that the switches can ping the host.

```
S2#ping 172.17.99.23
Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 172.17.99.23, timeout is 2 seconds:
!!!!
Success rate is 100 percent (5/5), round-trip min/avg/max = 1/202/1007 ms

S1#ping 172.17.99.23
Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 172.17.99.23, timeout is 2 seconds:
!!!!
Success rate is 100 percent (5/5), round-trip min/avg/max = 1/202/1007 ms
```

Put S1 in spanning-tree event debug mode to monitor changes during the topology change.

```
S1#debug spanning-tree events
Spanning Tree event debugging is on
```

Open a command window on PC3 and begin a continuous ping to the S1 management interface with the command **ping -t 172.17.99.11**. Now disconnect the trunks on S1 Fa0/1 and Fa0/3. Monitor the pings. They will begin to time out as connectivity across the LAN is interrupted. As soon as connectivity has been re-established, terminate the pings by pressing Ctrl-C.

Below is a shortened version of the debug output you will see on S1 (several TCNs are omitted for brevity).

```
S1#debug spanning-tree events
Spanning Tree event debugging is on
S1#
6d08h: STP: VLAN0099 new root port Fa0/2, cost 19
6d08h: STP: VLAN0099 Fa0/2 -> listening
6d08h: %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1,
changed state to down
6d08h: %LINK-3-UPDOWN: Interface FastEthernet0/1, changed state to down
6d08h: STP: VLAN0099 sent Topology Change Notice on Fa0/2
6d08h: STP: VLAN0030 Topology Change rcvd on Fa0/2
6d08h: %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/3,
changed state to down
6d08h: %LINK-3-UPDOWN: Interface FastEthernet0/3, changed state to down
6d08h: STP: VLAN0001 Topology Change rcvd on Fa0/4
6d08h: STP: VLAN0099 Fa0/2 -> learning
6d08h: STP: VLAN0099 sent Topology Change Notice on Fa0/2
6d08h: STP: VLAN0099 Fa0/2 -> forwarding
```

```
6d08h: STP: VLAN0001 Topology Change rcvd on Fa0/4
```

Recall that when the ports are in listening and learning mode, they are not forwarding frames, and the LAN is essentially down. The spanning tree recalculation can take up to 50 seconds to complete – a significant interruption in network services. The output of the continuous pings shows the actual interruption time. In this case, it was about 30 seconds. While 802.1D STP effectively prevents switching loops, this long restoration time is considered a serious drawback in the high availability LANs of today.




Figure 1. These pings show a 30-second lapse in connectivity while the spanning tree is recalculated.

### Task 8: Configure PVST Rapid Spanning Tree Protocol

Cisco has developed several features to address the slow convergence times associated with standard STP. PortFast, UplinkFast, and BackboneFast are features that, when properly configured, can dramatically reduce the time required to restore connectivity. Incorporating these features requires manual configuration, and care must be taken to do it correctly. The longer term solution is Rapid STP (RSTP), 802.1w, which incorporates these features among others. RSTP-PVST is configured as follows:

```
S1(config)#spanning-tree mode rapid-pvst
```

Configure all three switches in this manner.

Use the command **show spanning-tree summary** to verify that RSTP is enabled.

### Task 9: Observe the convergence time of RSTP

Begin by restoring the trunks you disconnected in Task 7, if you have not already done so (ports Fa0/1 and Fa0/3 on S1). Then follow these steps in Task 7:

- Set up host PC3 to continuously ping across the network.
- Enable spanning-tree event debugging on switch S1.
- Disconnect the cables connected to ports Fa0/1 and Fa0/3.
- Observe the time required to re-establish a stable spanning tree.

Below is the partial debug output:

```
S1#debug spanning-tree events
Spanning Tree event debugging is on
S1#
6d10h: RSTP(99): updt rolesroot port Fa0/3 is going down
```

```
6d10h: RSTP(99): Fa0/2 is now root port Connectivity has been restored; less than 1
second interruption
6d10h: RSTP(99): syncing port Fa0/1
6d10h: RSTP(99): syncing port Fa0/4
6d10h: RSTP(99): transmitting a proposal on Fa0/1
6d10h: RSTP(99): transmitting a proposal on Fa0/4
6d10h: %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/3,
changed state to down
6d10h: %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1,
changed state to down
```

The restoration time with RSTP enabled was less than a second, and not a single ping was dropped.

## Task 10: Clean Up

Erase the configurations and reload the default configurations for the switches. Disconnect and store the cabling. For PC hosts that are normally connected to other networks (such as the school LAN or to the Internet), reconnect the appropriate cabling and restore the TCP/IP settings.

## Final Configurations

### Switch S1

```
hostname S1
!
enable secret class
!
no ip domain-lookup
!
spanning-tree mode rapid-pvst
spanning-tree extend system-id
spanning-tree vlan 1 priority 4096
spanning-tree vlan 10 priority 4096
spanning-tree vlan 20 priority 4096
spanning-tree vlan 30 priority 4096
!
interface FastEthernet0/1
 switchport trunk native vlan 99
 switchport mode trunk
!
interface FastEthernet0/2
 switchport trunk native vlan 99
 switchport mode trunk
!
interface FastEthernet0/3
 switchport trunk native vlan 99
 switchport mode trunk
!
interface FastEthernet0/4
 switchport trunk native vlan 99
 switchport mode trunk
!
interface FastEthernet0/5
 shutdown
!
```

```
interface FastEthernet0/6
 shutdown
!
interface FastEthernet0/7
 shutdown
!
(remaining port configuration omitted - all non-used ports are shutdown)
!
!
interface Vlan1
 no ip address
 no ip route-cache
!
interface Vlan99
 ip address 172.17.99.11 255.255.255.0
 no ip route-cache
!
line con 0
 password cisco
 login
line vty 0 4
 password cisco
 login
line vty 5 15
 password cisco
 login
!
end
```

## Switch S2

```
hostname S2
!
enable secret class
!
no ip domain-lookup
!
interface FastEthernet0/1
 switchport trunk native vlan 99
 switchport mode trunk
!
interface FastEthernet0/2
 switchport trunk native vlan 99
 switchport mode trunk
!
interface FastEthernet0/3
 switchport trunk native vlan 99
 switchport mode trunk
!
interface FastEthernet0/4
 switchport trunk native vlan 99
 switchport mode trunk
!
interface FastEthernet0/5
 switchport access vlan 30
```



```
    switchport mode access
    shutdown
!
interface FastEthernet0/6
    switchport access vlan 30
    switchport mode access
!
interface FastEthernet0/7
    switchport access vlan 30
    switchport mode access
    shutdown
!
interface FastEthernet0/8
    switchport access vlan 30
    switchport mode access
    shutdown
!
interface FastEthernet0/9
    switchport access vlan 30
    switchport mode access
    shutdown
!
interface FastEthernet0/10
    switchport access vlan 30
    switchport mode access
    shutdown
!
interface FastEthernet0/11
    switchport access vlan 10
    switchport mode access
!
interface FastEthernet0/12
    switchport access vlan 10
    switchport mode access
    shutdown
!
interface FastEthernet0/13
    switchport access vlan 10
    switchport mode access
    shutdown
!
interface FastEthernet0/14
    switchport access vlan 10
    switchport mode access
    shutdown
!
interface FastEthernet0/15
    switchport access vlan 10
    switchport mode access
    shutdown
!
interface FastEthernet0/16
    switchport access vlan 10
    switchport mode access
    shutdown
!
```

```
interface FastEthernet0/17
  switchport access vlan 10
  switchport mode access
  shutdown
!
interface FastEthernet0/18
  switchport access vlan 20
  switchport mode access
!
interface FastEthernet0/19
  switchport access vlan 20
  switchport mode access
  shutdown
!
interface FastEthernet0/20
  switchport access vlan 20
  switchport mode access
  shutdown
!
interface FastEthernet0/21
  switchport access vlan 20
  switchport mode access
  shutdown
!
interface FastEthernet0/22
  switchport access vlan 20
  switchport mode access
  shutdown
!
interface FastEthernet0/23
  switchport access vlan 20
  switchport mode access
  shutdown
!
interface FastEthernet0/24
  switchport access vlan 20
  switchport mode access
  shutdown
!
interface GigabitEthernet0/1
  shutdown
!
interface GigabitEthernet0/2
  shutdown
!
interface Vlan1
  no ip address
  no ip route-cache
!
interface Vlan99
  ip address 172.17.99.12 255.255.255.0
  no ip route-cache
!
line con 0
line vty 0 4
  password cisco
```

```
login
line vty 5 15
password cisco
login
!
end
```


### Switch S3

```
hostname S3
!
enable secret class
!
no ip domain-lookup
!
spanning-tree mode rapid-pvst
spanning-tree extend system-id
spanning-tree vlan 99 priority 4096
!
interface FastEthernet0/1
switchport trunk native vlan 99
switchport mode trunk
!
interface FastEthernet0/2
switchport trunk native vlan 99
switchport mode trunk
!
interface FastEthernet0/3
switchport trunk native vlan 99
switchport mode trunk
!
interface FastEthernet0/4
switchport trunk native vlan 99
switchport mode trunk
!
interface FastEthernet0/5
shutdown
!
interface FastEthernet0/6
shutdown
!
interface FastEthernet0/7
shutdown
!
(remaining port configuration omitted - all non-used ports are shutdown)
!
interface Vlan1
no ip address
no ip route-cache
shutdown
!
interface Vlan99
ip address 172.17.99.13 255.255.255.0
no ip route-cache
!
```

```
line con 0
  password cisco
  login
line vty 0 4
  password cisco
  login
line vty 5 15
  password cisco
  login
!
end
```

## Lab 6.4.1: Basic Inter-VLAN Routing

### Topology Diagram



### Addressing Table

Device (Hostname)	Interface	IP Address	Subnet Mask	Default Gateway
S1	VLAN 99	172.17.99.11	255.255.255.0	172.17.99.1
S2	VLAN 99	172.17.99.12	255.255.255.0	172.17.99.1
S3	VLAN 99	172.17.99.13	255.255.255.0	172.17.99.1

<b>R1</b>	<b>Fa 0/0</b>	172.17.50.1	255.255.255.0	N/A
<b>R1</b>	<b>Fa 0/1</b>	See Interface Configuration Table		N/A
<b>PC1</b>	<b>NIC</b>	172.17.10.21	255.255.255.0	172.17.10.1
<b>PC2</b>	<b>NIC</b>	172.17.20.22	255.255.255.0	172.17.20.1
<b>PC3</b>	<b>NIC</b>	172.17.30.23	255.255.255.0	172.17.30.1
<b>Server</b>	<b>NIC</b>	172.17.50.254	255.255.255.0	172.17.50.1

## Port Assignments – Switch 2

Ports	Assignment	Network
Fa0/1 – 0/5	802.1q Trunks (Native VLAN 99)	172.17.99.0 /24
Fa0/6 – 0/10	VLAN 30 – Guest (Default)	172.17.30.0 /24
Fa0/11 – 0/17	VLAN 10 – Faculty/Staff	172.17.10.0 /24
Fa0/18 – 0/24	VLAN 20 - Students	172.17.20.0 /24

## Interface Configuration Table – Router 1

Interface	Assignment	IP Address
Fa0/1.1	VLAN1	172.17.1.1 /24
Fa0/1.10	VLAN 10	172.17.10.1 /24
Fa0/1.20	VLAN 20	172.17.20.1 /24
Fa0/1.30	VLAN 30	172.17.30.1 /24
Fa0/1.99	VLAN 99	172.17.99.1 /24

## Learning Objectives

Upon completion of this lab, you will be able to:

- Cable a network according to the topology diagram
- Clear configurations and reload a switch and a router to the default state
- Perform basic configuration tasks on a switched LAN and router
- Configure VLANs and VLAN Trunking Protocol (VTP) on all switches
- Demonstrate and explain the impact of Layer 3 boundaries imposed by creating VLANs
- Configure a router to support 802.1q trunking on a Fast Ethernet interface
- Configure a router with subinterfaces corresponding to the configured VLANs
- Demonstrate and explain inter-VLAN routing

## Task 1: Prepare the Network

### Step 1: Cable a network that is similar to the one in the topology diagram.

The output shown in this lab is based on 2960 switches and an 1841 router. You can use any current switches or routers in your lab as long as they have the required interfaces shown in the topology diagram. Other device types may produce different output. Note that Ethernet (10Mb) LAN interfaces on routers do not support trunking, and Cisco IOS software earlier than version 12.3 may not support trunking on Fast Ethernet router interfaces.

Set up console connections to all three switches and to the router.

### Step 2: Clear any existing configurations on the switches.

Clear NVRAM, delete the vlan.dat file, and reload the switches. Refer to lab 2.2.1 if necessary for the procedure. After the reload is complete, use the **show vlan** command to confirm that only default VLANs exist and that all ports are assigned to VLAN 1.

Switch#**show vlan**

VLAN	Name	Status	Ports
1	default	active	Fa0/1, Fa0/2, Fa0/3, Fa0/4 Fa0/5, Fa0/6, Fa0/7, Fa0/8 Fa0/9, Fa0/10, Fa0/11, Fa0/12 Fa0/13, Fa0/14, Fa0/15, Fa0/16 Fa0/17, Fa0/18, Fa0/19, Fa0/20 Fa0/21, Fa0/22, Fa0/23, Fa0/24 Gig0/1, Gig0/2
1002	fddi-default	active	
1003	token-ring-default	active	
1004	fddinet-default	active	
1005	trnet-default	active	

### Step 3: Disable all ports using the shutdown command.

Ensure that the initial switch port states are inactive by disabling all ports. Use the **interface range** command to simplify this task. Repeat these commands on each switch in the topology.

```
Switch(config)#interface range fa0/1-24
Switch(config-if-range)#shutdown
Switch(config-if-range)#interface range gi0/1-2
Switch(config-if-range)#shutdown
```

## Task 2: Perform Basic Switch Configurations

### Step 1: Configure the S1, S2, and S3 switches.

Use the addressing table and the following guidelines:

- Configure the switch hostname.
- Disable DNS lookup.
- Configure an enable secret password of **class**.
- Configure a password of **cisco** for console connections.
- Configure a password of **cisco** for vty connections.
- Configure the default gateway on each switch

#### Output for S1 shown

```
Switch>enable
Switch#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#hostname S1
S1(config)#enable secret class
S1(config)#no ip domain-lookup
S1(config)#ip default-gateway 172.17.99.1
```

```
S1(config)#line console 0
S1(config-line)#password cisco
S1(config-line)#login
S1(config-line)#line vty 0 15
S1(config-line)#password cisco
S1(config-line)#login
S1(config-line)#end
%SYS-5-CONFIG_I: Configured from console by console
S1#copy running-config startup-config
Destination filename [startup-config]? [enter]
Building configuration...
```

**Step 2: Re-enable the active user ports on S2 in access mode.**

```
S2(config)#interface fa0/6
S2(config-if)#switchport mode access
S2(config-if)#no shutdown
S2(config-if)#interface fa0/11
S2(config-if)#switchport mode access
S2(config-if)#no shutdown
S2(config-if)#interface fa0/18
S2(config-if)#switchport mode access
S2(config-if)#no shutdown
```

**Task 3: Configure the Ethernet Interfaces on the Host PCs**

Configure the Ethernet interfaces of PC1, PC2, PC3 and the remote TFTP/Web Server with the IP addresses from the addressing table.

**Task 4: Configure VTP on the Switches**

**Step 1: Configure VTP on the three switches using the following table. Remember that VTP domain names and passwords are case-sensitive.**

Switch Name	VTP Operating Mode	VTP Domain	VTP Password
S1	Server	Lab6	cisco
S2	Client	Lab6	cisco
S3	Client	Lab6	cisco

**S1:**

```
S1(config)#vtp mode server
Device mode already VTP SERVER.
S1(config)#vtp domain Lab6
Changing VTP domain name from NULL to Lab6
S1(config)#vtp password cisco
Setting device VLAN database password to cisco
S1(config)#end
```

**S2:**

```
S2(config)#vtp mode client
```



```
Setting device to VTP CLIENT mode
S2(config)#vtp domain Lab6
Changing VTP domain name from NULL to Lab6
S2(config)#vtp password cisco
Setting device VLAN database password to cisco
S2(config)#end
```

### S3:

```
S3(config)#vtp mode client
Setting device to VTP CLIENT mode
S3(config)#vtp domain Lab6
Changing VTP domain name from NULL to Lab6
S3(config)#vtp password cisco
Setting device VLAN database password to cisco
S3(config)#end
```

### Step 2: Configure trunking ports and designate the native VLAN for the trunks.

Configure Fa0/1 through Fa0/5 as trunking ports, and designate VLAN 99 as the native VLAN for these trunks. Use the **interface range** command in global configuration mode to simplify this task.

```
S1(config)#interface range fa0/1-5
S1(config-if-range)#switchport mode trunk
S1(config-if-range)#switchport trunk native vlan 99
S1(config-if-range)#no shutdown
S1(config-if-range)#end

S2(config)# interface range fa0/1-5
S2(config-if-range)#switchport mode trunk
S2(config-if-range)#switchport trunk native vlan 99
S2(config-if-range)#no shutdown
S2(config-if-range)#end

S3(config)# interface range fa0/1-5
S3(config-if-range)#switchport mode trunk
S3(config-if-range)#switchport trunk native vlan 99
S3(config-if-range)#no shutdown
S3(config-if-range)#end
```

### Step 3: Configure VLANs on the VTP server.

Configure the following VLANs on the VTP server:

VLAN	VLAN Name
VLAN 99	management
VLAN 10	faculty-staff
VLAN 20	students
VLAN 30	guest

```
S1(config)#vlan 99
S1(config-vlan)#name management
S1(config-vlan)#exit
S1(config)#vlan 10
```

```
S1(config-vlan)#name faculty-staff
S1(config-vlan)#exit
S1(config)#vlan 20
S1(config-vlan)#name students
S1(config-vlan)#exit
S1(config)#vlan 30
S1(config-vlan)#name guest
S1(config-vlan)#end
```

Verify that the VLANs have been created on S1 with the **show vlan brief** command.

#### Step 4: Verify that the VLANs created on S1 have been distributed to S2 and S3.

Use the **show vlan brief** command on S2 and S3 to verify that the four VLANs have been distributed to the client switches.

```
S2#show vlan brief
```

VLAN	Name	Status	Ports
1	default	active	Fa0/1, Fa0/2, Fa0/4, Fa0/5 Fa0/6, Fa0/7, Fa0/8, Fa0/9 Fa0/10, Fa0/11, Fa0/12, Fa0/13 Fa0/14, Fa0/15, Fa0/16, Fa0/17 Fa0/18, Fa0/19, Fa0/20, Fa0/21 Fa0/22, Fa0/23, Fa0/24, Gi0/1 Gi0/2
10	faculty-staff	active	
20	students	active	
30	guest	active	
99	management	active	

#### Step 5: Configure the management interface address on all three switches.

```
S1(config)#interface vlan 99
S1(config-if)#ip address 172.17.99.11 255.255.255.0
S1(config-if)#no shutdown
S1(config-if)#end
```

```
S2(config)#interface vlan 99
S2(config-if)#ip address 172.17.99.12 255.255.255.0
S2(config-if)#no shutdown
S2(config-if)#end
```

```
S3(config)#interface vlan 99
S3(config-if)#ip address 172.17.99.13 255.255.255.0
S3(config-if)#no shutdown
S3(config-if)#end
```

Verify that the switches are correctly configured by pinging between them. From S1, ping the management interface on S2 and S3. From S2, ping the management interface on S3.

Were the pings successful? \_\_\_\_\_

If not, troubleshoot the switch configurations and try again.

#### Step 6: Assign switch ports to VLANs on S2.

Refer to the port assignments table at the beginning of the lab to assign ports to VLANs on S2.

```
S2(config)#interface range fa0/6-10
S2(config-if-range)#switchport access vlan 30
S2(config-if-range)#interface range fa0/11-17
S2(config-if-range)#switchport access vlan 10
S2(config-if-range)#interface range fa0/18-24
S2(config-if-range)#switchport access vlan 20
S2(config-if-range)#end
S2#copy running-config startup-config
Destination filename [startup-config]? [enter]
Building configuration...
[OK]
```

### Step 7: Check connectivity between VLANs.

Open command windows on the three hosts connected to S2. Ping from PC1 (172.17.10.21) to PC2 (172.17.20.22). Ping from PC2 to PC3 (172.17.30.23).

Are the pings successful? \_\_\_\_\_

If not, why do these pings fail? \_\_\_\_\_

\_\_\_\_\_

## Task 5: Configure the Router and the Remote Server LAN

### Step 1: Clear the configuration on the router and reload.

```
Router#erase nvram:
Erasing the nvram filesystem will remove all configuration files! Continue?
[confirm]
Erase of nvram: complete
Router#reload
System configuration has been modified. Save? [yes/no]: no
```

### Step 2: Create a basic configuration on the router.

- Configure the router with hostname R1.
- Disable DNS lookup.
- Configure an EXEC mode password of **cisco**.
- Configure a password of **cisco** for console connections.
- Configure a password of **cisco** for vty connections.

### Step 3: Configure the trunking interface on R1.

You have demonstrated that connectivity between VLANs requires routing at the network layer, exactly like connectivity between any two remote networks. There are a couple of options for configuring routing between VLANs.

The first is something of a brute force approach. An L3 device, either a router or a Layer 3 capable switch, is connected to a LAN switch with multiple connections—a separate connection for each VLAN that requires inter-VLAN connectivity. Each of the switch ports used by the L3 device is configured in a different VLAN on the switch. After IP addresses are assigned to the interfaces on the L3 device, the routing table has directly connected routes for all VLANs, and inter-VLAN routing is enabled. The limitations to this approach are the lack of sufficient Fast Ethernet ports on routers, under-utilization of

ports on L3 switches and routers, and excessive wiring and manual configuration. The topology used in this lab does not use this approach.

An alternative approach is to create one or more Fast Ethernet connections between the L3 device (the router) and the distribution layer switch, and to configure these connections as dot1q trunks. This allows all inter-VLAN traffic to be carried to and from the routing device on a single trunk. However, it requires that the L3 interface be configured with multiple IP addresses. This can be done by creating “virtual” interfaces, called subinterfaces, on one of the router Fast Ethernet ports and configuring them to dot1q aware.

Using the subinterface configuration approach requires these steps:

- Enter subinterface configuration mode
- Establish trunking encapsulation
- Associate a VLAN with the subinterface
- Assign an IP address from the VLAN to the subinterface

The commands are as follows:

```
R1(config)#interface fastethernet 0/1
R1(config-if)#no shutdown

R1(config-if)#interface fastethernet 0/1.1
R1(config-subif)#encapsulation dot1q 1
R1(config-subif)#ip address 172.17.1.1 255.255.255.0

R1(config-if)#interface fastethernet 0/1.10
R1(config-subif)#encapsulation dot1q 10
R1(config-subif)#ip address 172.17.10.1 255.255.255.0

R1(config-if)#interface fastethernet 0/1.20
R1(config-subif)#encapsulation dot1q 20
R1(config-subif)#ip address 172.17.20.1 255.255.255.0

R1(config-if)#interface fastethernet 0/1.30
R1(config-subif)#encapsulation dot1q 30
R1(config-subif)#ip address 172.17.30.1 255.255.255.0

R1(config-if)#interface fastethernet 0/1.99
R1(config-subif)#encapsulation dot1q 99 native
R1(config-subif)#ip address 172.17.99.1 255.255.255.0
```

Note the following points in this configuration:

- The physical interface is enabled using the **no shutdown** command, because router interfaces are down by default. The virtual interfaces are up by default.
- The subinterface can use any number that can be described with 32 bits, but it is good practice to assign the number of the VLAN as the interface number, as has been done here.
- The native VLAN is specified on the L3 device so that it is consistent with the switches. Otherwise, VLAN 1 would be the native VLAN by default, and there would be no communication between the router and the management VLAN on the switches.

Confirm creation and status of the subinterfaces with the **show ip interface brief** command:

```
R1#show ip interface brief
Interface          IP-Address      OK? Method Status          Protocol
```

FastEthernet0/0	unassigned	YES	unset	administratively down	down
FastEthernet0/1	unassigned	YES	unset	up	up
FastEthernet0/1.1	172.17.1.1	YES	manual	up	up
FastEthernet0/1.10	172.17.10.1	YES	manual	up	up
FastEthernet0/1.20	172.17.20.1	YES	manual	up	up
FastEthernet0/1.30	172.17.30.1	YES	manual	up	up
FastEthernet0/1.99	172.17.99.1	YES	manual	up	up

#### Step 4: Configure the server LAN interface on R1.

```
R1(config)# interface FastEthernet0/0
R1(config-if)#ip address 172.17.50.1 255.255.255.0
R1(config-if)#description server interface
R1(config-if)#no shutdown
R1(config-if)#end
```

There are now six networks configured. Verify that you can route packets to all six by checking the routing table on R1.

```
R1#show ip route
<output omitted>
```

Gateway of last resort is not set

```
172.17.0.0/24 is subnetted, 6 subnets
C    172.17.50.0 is directly connected, FastEthernet0/0
C    172.17.30.0 is directly connected, FastEthernet0/1.30
C    172.17.20.0 is directly connected, FastEthernet0/1.20
C    172.17.10.0 is directly connected, FastEthernet0/1.10
C    172.17.1.0 is directly connected, FastEthernet0/1.1
C    172.17.99.0 is directly connected, FastEthernet0/1.99
```

If your routing table does not show all six networks, troubleshoot your configuration and resolve the problem before proceeding.

#### Step 5: Verify Inter-VLAN routing.

From PC1, verify that you can ping the remote server (172.17.50.254) and the other two hosts (172.17.20.22 and 172.17.30.23). It may take a couple of pings before the end-to-end path is established.

Are the pings successful? \_\_\_\_\_

If not, troubleshoot your configuration. Check to make sure that the default gateways have been set on all PCs and all switches. If any of the hosts have gone into hibernation, the connected interface may go down.

#### Task 6: Reflection

In Task 5, it was recommended that you configure VLAN 99 as the native VLAN in the router Fa0/0.99 interface configuration. Why would packets from the router or hosts fail when trying to reach the switch management interfaces if the native VLAN were left in default?

---



---



---



---

## Task 7: Clean Up

Erase the configurations and reload the switches. Disconnect and store the cabling. For PC hosts that are normally connected to other networks (such as the school LAN or to the Internet), reconnect the appropriate cabling and restore the TCP/IP settings.

## Final Configurations

### Router 1

```
hostname R1
!
enable secret class
!
no ip domain lookup
!
interface FastEthernet0/0
 ip address 172.17.50.1 255.255.255.0
 no shutdown
!
interface FastEthernet0/1
 no shutdown
!
interface FastEthernet0/1.1
 encapsulation dot1Q 1
 ip address 172.17.1.1 255.255.255.0
!
interface FastEthernet0/1.10
 encapsulation dot1Q 10
 ip address 172.17.10.1 255.255.255.0
!
interface FastEthernet0/1.20
 encapsulation dot1Q 20
 ip address 172.17.20.1 255.255.255.0
!
interface FastEthernet0/1.30
 encapsulation dot1Q 30
 ip address 172.17.30.1 255.255.255.0
!
interface FastEthernet0/1.99
 encapsulation dot1Q 99 native
 ip address 172.17.99.1 255.255.255.0
!
<output omitted - serial interfaces not configured>
!
line con 0
line aux 0
line vty 0 4
 login
 password cisco
!
```

### Switch 1

```
!
hostname S1
!
```

```
enable secret class
!
no ip domain lookup
!
interface FastEthernet0/1
    switchport trunk native vlan 99
    switchport mode trunk
!
interface FastEthernet0/2
    switchport trunk native vlan 99
    switchport mode trunk
!
interface FastEthernet0/3
    switchport trunk native vlan 99
    switchport mode trunk
!
interface FastEthernet0/4
    switchport trunk native vlan 99
    switchport mode trunk
!
interface FastEthernet0/5
    switchport trunk native vlan 99
    switchport mode trunk
!
<output omitted - all remaining ports in shutdown>
!
interface Vlan1
    no ip address
    no ip route-cache
!
interface Vlan99
    ip address 172.17.99.11 255.255.255.0
    no shutdown
!
ip default-gateway 172.17.99.1
ip http server
!
line con 0
    logging synchronous
line vty 0 4
    login
    password cisco
line vty 5 15
    login
    password cisco
```

## Switch 2

```
!
hostname S2
!
enable secret class
!
no ip domain lookup
!
interface FastEthernet0/1
    switchport trunk native vlan 99
```

```
    switchport mode trunk
!
interface FastEthernet0/2
    switchport trunk native vlan 99
    switchport mode trunk
!
interface FastEthernet0/3
    switchport trunk native vlan 99
    switchport mode trunk
!
interface FastEthernet0/4
    switchport trunk native vlan 99
    switchport mode trunk
!
interface FastEthernet0/5
    switchport trunk native vlan 99
    switchport mode trunk
!
    interface FastEthernet0/6
        switchport access vlan 30
        switchport mode access
    !
interface FastEthernet0/7
    switchport access vlan 30
!
interface FastEthernet0/8
    switchport access vlan 30
!
interface FastEthernet0/9
    switchport access vlan 30
!
interface FastEthernet0/10
    switchport access vlan 30
!
interface FastEthernet0/11
    switchport access vlan 10
    switchport mode access
!
interface FastEthernet0/12
    switchport access vlan 10
!
interface FastEthernet0/13
    switchport access vlan 10
!
interface FastEthernet0/14
    switchport access vlan 10
!
interface FastEthernet0/15
    switchport access vlan 10
!
interface FastEthernet0/16
    switchport access vlan 10
!
interface FastEthernet0/17
    switchport access vlan 10
!
```



```
interface FastEthernet0/18
  switchport access vlan 20
!
interface FastEthernet0/19
  switchport access vlan 20
!
interface FastEthernet0/20
  switchport access vlan 20
!
interface FastEthernet0/21
  switchport access vlan 20
!
interface FastEthernet0/22
  switchport access vlan 20
!
interface FastEthernet0/23
  switchport access vlan 20
!
interface FastEthernet0/24
  switchport access vlan 20
!
interface Vlan1
  no ip address
  no ip route-cache
!
interface Vlan99
  ip address 172.17.99.12 255.255.255.0
  no shutdown
!
ip default-gateway 172.17.99.1
ip http server
!
line con 0
  password cisco
  logging synchronous
  login
line vty 0 4
  password cisco
  login
line vty 5 15
  password cisco
  login
!
end
```

### Switch 3

```
!
hostname S3
!
enable secret class
!
no ip domain lookup
!
interface FastEthernet0/1
  switchport trunk native vlan 99
```

```
    switchport mode trunk
!
interface FastEthernet0/2
    switchport trunk native vlan 99
    switchport mode trunk
!
interface FastEthernet0/3
    switchport trunk native vlan 99
    switchport mode trunk
!
interface FastEthernet0/4
    switchport trunk native vlan 99
    switchport mode trunk
!
interface FastEthernet0/5
    switchport trunk native vlan 99
    switchport mode trunk
!
<output omitted - all remaining ports in shutdown>
!
interface Vlan99
    ip address 172.17.99.13 255.255.255.0
    no shutdown
!
ip default-gateway 172.17.99.1
ip http server
!
control-plane
!
line con 0
    password cisco
    login
line vty 0 4
    password cisco
    login
line vty 5 15
    password cisco
    login
!
end
```